Option Section	Option Name	Option Notes
Minimum Score	Minimum score required to pass the test	Insert a number into the text box to set the minimum score a user must make in order to pass the test.
Score Display	Express score as numbers	
Please Note: You cannot configure this section if a user has already started the test.	Express score as percentage	
Manage Score per Question	Current Maximum Score	This is not a field that is directly editable by you. It is automatically calculated based on how you configure the rest of the scoring options.
Please note that these options differ if you've imported a question from the Question Bank into the test.	New Maximum Score	This field is conditional to whether there are questions from the question bank imported into the test. This field will be recalculated based on the score set for any question from the question bank that is placed within the test (as this score for these types of questions are absolute) combined with individual scores set for local questions in the test. The max score must be greater than the sum total of points coming from Question Bank questions in this test.
	Do Nothing	For this option, the score will not be distributed and divided among the questions. This option is not affected if there are any questions from the question bank imported into the test.
	Score based on question's level of difficulty	For this option, you need to type the total score of the exam in the corresponding text box. Then, in the Set Level of Difficulty column for each question, you need to set whether a question is very easy, easy, medium, hard, or very hard. From here, your platform will automatically delegate how many points are assigned to each question. This option will not be applied to any questions in the test that are imported from the question bank. Please note that if you add a new question to the test after setting this option, it will not be taken into consideration in the score calculation until you save your settings to recalculate the score distribution among all the questions, including the last one.
	Same score for each question (total score divided by displayed number of questions)	For this option, you need to type the total score of the exam in the corresponding text box. The points will them be distributed evenly among the questions. Please note that you cannot configure this option if the test contains any questions imported from the question bank. Questions that are not presented to the user are not calculated in the final score. Please note that if you add a new question to the test after setting this option, it will not be taken into

		consideration in the score calculation until you save your settings to recalculate the score distribution among all the questions, including the last one.
	Choose score for every question	For this option, you will type the score you want for each individual question in each question's row. The difficulty that you set for each question will not influence the score if you flag this option. When you're finished and you have saved your changes, you will see the total score of the exam, as calculated by your LMS, at the top of this option. This option will not be applied to any questions in the test that are imported from the question bank. Remember that the default score for a question added is "0" unless otherwise specified by an update on the Set Difficulty and Score for Each Question area of the Score Management page.
	Same point for each visible question (total score /number of questions in test)	This option is only if you have flagged the Random choice of questions from the number of questions available option in the Questions section of the Test Options area. For each answer that appears in the test, the score will be distributed evenly among each question. Please note that you cannot configure this option if the test contains any questions imported from the question bank. Please note that if you add a new question to the test after setting this option, it will not be taken into consideration in the score calculation until you save your settings to recalculate the score distribution among all the questions, including the last one.